


Ulead® DVD Workshop™ 2 Quick Guide

The Ulead DVD Workshop Quick Guide was made to help you quickly create your projects and burn them onto a disc. Follow the procedure below to quickly produce your discs.

1. Create a new project
2. Import and add clips
3. Edit your clips
4. Create your menu
5. Preview and burn your project


Create a new project



Click **New Project** and then in the New Project dialog box, enter the necessary information in the fields and click **OK**.


Tip: For **Media type** and **TV System**, make sure you know the output disc and TV standard you want because you won't be able to change this later.

Import and add clips




In the **Edit Step**, import the clips you want to use for your project into the Library.



Tip: Click **Edit** in the **Step Panel** to go to the Edit Step.



To import clips into the library, first, switch to the media clip type tab you want to import. To do this, click the **arrow** on the Library tab then select the type of media clip you want to import.

Next, click  then in the dialog box that opens, select the file(s) you want to import then click **Open**.

After importing clips to the Library, add clips to your project.



Drag and drop the clips you want to include in your project to blank placeholders labeled **New Title** in the Title List. To make a clip as your **First Play Video***, drag and drop the clip to the **First Play** placeholder (first placeholder in the Title List).

Tip: To create a slideshow, select (press **[Ctrl]** +click to select multiple images) the images you want to include in your slideshow from the Library then drag and drop them to a blank placeholder. Customize it by adding a transition effect through the Options Panel.

* First Play Video is the clip that is played before the menu of your movie is shown.

Edit your clips

Trim your clips and insert chapters for your menus using the **Navigation Panel**. Chapters are entry points in your video that viewers can instantly access through the menu.


To insert chapters*, use the Navigation Panel to search for the part of the video you want to insert as a chapter point.



When you get to the part of the video that you want to insert as a chapter, click **Add Chapter** in the Options Panel.

Tip: Click **Auto Add Chapters** to open a dialog box where you can automatically insert the different scenes in your clip as chapters.

* You can have a maximum of 99 chapters for each video and slideshow.



Add Chapter


The chapters that you inserted will be displayed in the **Chapter List**.

Tips:

- To delete a chapter, right-click the chapter thumbnail you want to delete and select **Delete Chapter** on the pop-up menu.
- To set an image as a chapter in slideshows, right-click the image then select **Mark as Chapter**. Only chapters in a slideshow can be added to your menus.



For DVD projects, you can add extra audio and subtitle tracks to your videos. To do this, click the **Audio/Subtitle** tab.


To add extra audio tracks, select the **Audio** tab then click . In the **Load Audio File** dialog box, locate the audio track then click **Open**.


To add subtitle tracks, select the **Subtitle** tab then click **Add/Edit Subtitle**. In the **Add/Edit Subtitle** dialog box, create your subtitle tracks by typing in the subtitle text and setting the time for each subtitle segment. After you have created your subtitle tracks, click **OK**.



Customize the appearance and position of the subtitle text through the various text options available.

Tips:

- You can also type the subtitle text directly on the **Preview Window**. To do this, click on the **Preview Window** and type in your text.
- After closing the **Add/Edit Subtitle** dialog box, you can preview the different audio and subtitle tracks in your project. To switch to a different audio and/or subtitle track, click  in the **Navigation Panel** then select the audio and/or subtitle track you want to preview.



Create your menu

Click **Menu** in the **Step Panel** to create your menu. Menus allow viewers to navigate through the different chapters and/or videos and select different audio and subtitle tracks.



Create a new menu by clicking one of the 3 buttons above the Content Window. You can select either to create a **blank menu**, use a **menu template** or use the **Menu Wizard**.

Use these buttons to show/hide **button information**, **highlight images**, **object boundaries** and/or **grid lines**.

After selecting the type of menu, build your menu by dragging and dropping objects such as images and videos into the Preview Window. Add text objects by double-clicking on the Preview Window.

Any object added to the menu can act as either decorations or buttons. Buttons are objects that act as links to the different elements in your menu. To create buttons, simply drag and drop the item you want the object to link to- either a menu, chapter or title- to the object.

Note: Dragging and dropping an item from the **Chapter List** or **Content Window** to the Preview Window automatically creates a button.

After creating a button, you can further customize its behavior by creating a playlist. To create a playlist, select **Playlist** in either the **Button** or **Text** tab depending on the type of the button.

Drag and drop the items (menu, chapters or titles) you want included in the button's playlist into the **Playlist window** then arrange the sequence of the items or add new items using the available buttons.

Tip when creating menus in a DVD project:

Spice up your menus by using animated backgrounds and buttons. Simply drag-and-drop video files from the Library into the Preview Window and select **Motion Background** and **Motion Button** in the **Menu** and **Button** tabs. You can then preview your motion background and buttons in real-time by clicking **Play** in the **Navigation Panel**.

Preview and burn your project


Click **Finish** in the **Step Panel** to preview your project in the Preview Window. To preview the behavior of your menu, the actual video, and audio and subtitle tracks (if any), use the buttons on the remote control.



To burn your project onto a disc, click **Burn Project to Disc** on the remote control. In the Burn Project to Disc dialog box, select the options you want in the **Burn** and **Advanced Settings** tabs, then click **Burn**.

Tips:

- Select **Create DVD folders** if you want to save and play your DVD title in your computer. You will need a DVD software player to play back your DVD.
- Select **Create disc image file** to create a disc image of your project on your hard drive. Select this if you intend to burn several copies of your project onto discs.
- In the **Advanced Settings** tab, you can set the **Region code** for your DVD to limit the countries where your DVD can be played back. However, this will also depend on the DVD player's playback capabilities.



Click **Write Disc Image to DLT** to output your project to a Digital Linear Tape (DLT). Most production houses require DLTs if you want to mass reproduce your DVD.

Tip: DVD Workshop supports outputting to DVD-9 (single-side dual-layer) format and also gives you the option of outputting your DVDs with CSS encryption to prevent duplication of your DVDs. These options can be found inside the **Ulead DLT Writer** dialog box.